Tutorial for Light Linking (Light-Centric and Object-Centric)

There are 2 options in the Light Linking menu to control whether a light is able to illuminate an object: Light-Centric and Object-Centric.

Below is an example of a simple lighting setup with a Key and Rim light.

Currently, the problem is that the Back/Rim Light is casting a strong light on the floor/ ground plane, which is why the cast shadow cannot be seen.

There are 2 ways to get the Back/Rim light to un-illuminate the floor/ ground plane.

IMPORTANT NOTE: Sometimes, the light-linking in Maya can be buggy and a scene can only use one method of light-linking. So, if the light-centric is not working, try switching to object centric.

BE CAREFUL. When light linking and you go to save your file, Maya does not seem to recognize the changes made if that was the only thing you've done since your previous save.

So if you saved before light linking, then light linked, then incremental saved again, it will for some reason say "No changes to save". Be careful of this and make another change or "Save As" the file to the desired filename.





Option 1: Light-Centric

Step 1: Go to the **Outliner** OR the **Hypergraph: Hierarchy.** Select the light you do not want illuminating an object/GEO.

Outliner

Hypergraph: Hierarchy





Step 2: Go to "Windows" → "Relationship Editors" → "Light Linking" → "Light-Centric"

Step 3: Under the "Light Sources" (left) column, select the light.

Then, under the "Illuminated Objects" (right) column, select the GEO that you do not want the light to illuminate. The GEO will no longer be highlighted in blue.

M Relationship Editor	- 0	×
Options Help Light centric light linking 🔻		
Light centric light linking Light Sources List Edit Show Search GRP_LIGHTS GRP_LIGHTS Key Rim H (*) defaultLightSet	Illuminated Objects List Edit Show Search GRP_GEO Sphere_GEO Sphere_GEO SaiStandardSurface1SG SinitialParticleSE SinitialShadingGroup	
4		•



You'll see that there is still some light from the Rim Light bouncing from the sphere onto the floor.

To get rid of that we'll turn off Indirect Visibilty on the Rim Light.

Step 4: Select the Rim Light itself in either the Outliner or the Hypergraph: Hierarchy. Then, in the Attribute Editor, under the "Visibility" options, move the "Indirect" slider down to 0. Now that bouncing light should be gone!

List Selected Focus Attri Rim RimShape defau aiAreaLight: F Drawdb	butes Show Help ItLightSet LimShape	Focus Presets Show Hide		
Geometry Light Arnold Arealight				
Arnold Area Light Attrib			ि <u>वि</u>	
Color				
Intensity	3000.000			
Exposure	0.000		- I ttrib	
1	Use Color Temperature		uteE	
Temperature			dito	
	🖌 Illuminates By Default			
Light Shape				
Spread	1.000			
Resolution	512			
Roundness	0.000			
Soft Edge	0.000		- 🛃	
Samples	1			
	🖌 Normalize			
	🖌 Cast Shadows			
Shadow Density	1.000			
Shadow Color			-	
Cast Volumetric Shadows				
Volume Samples	2			
▼ Visibility				
Diffuse	1.000		1 -	
Specular	1.000			
SSS	1.000			
Indirect	0.000			
Volume	1.000		1 -	
N P		-	-	
Select	Load Attributes	Copy 1	īab	



See next page for Object-Centric Linking.

Option 2: Object-Centric

Step 1: Select the <u>GEO</u> you do not want a light to illuminate in either the **Outliner** or the **Hypergraph: Hierarchy**.

Outliner



Hypergraph: Hierarchy





Step 2: Go to "Windows" \rightarrow "Relationship Editors" \rightarrow "Light Linking" \rightarrow "Object-Centric"

Step 3:

Under the "Illuminated Objects" (left) column, select the GEO that you want to un-illuminate. Then, under the "Light Sources" (right) column, select the light that you do not want it to illuminate the GEO. The light will no longer be highlighted in blue.



Again, you'll see that there is still some light from the Rim Light bouncing from the sphere onto the floor.



To get rid of that we'll turn off Indirect Visibility on the Rim Light.

Step 4: Select the Rim Light itself in either the Outliner or the Hypergraph:Hierarchy. Then, in the Attribute Editor, under the "Visibility" options, move the "Indirect" slider down to 0. Now that bouncing light should be gone!

List Selected Focus Attributes Show Help				
Rim RimShape defau				
		Focus		
aiAreaLight:	RimShape	Presets		
		Show Hide		
Drawdb				
Light				
Arnold Arealight				
Arnold Area Light Attri		a 🖞		
Color		8 8		
Intensity	3000.000	••••		
Exposure	0.000	l iii		
	Use Color Temperature	uteg		
Temperature		dite		
	🗸 Illuminates By Default			
Light Shape				
Spread	1.000	1.8		
Resolution	512			
Roundness	0.000			
Soft Edge	0.000			
Samples	1			
	🖌 Normalize			
	 Cast Shadows 			
Shadow Density	1.000			
Shadow Colo		•		
	 Cast Volumetric Shadows 			
Volume Samples	2			
▼ Visibility				
Diffuse	1.000			
Specular	1.000			
SSS	1.000			
Indirect	0.000			
Volume	1.000	1 8		
· · · · · · · · · · · · · · · · · · ·	[]	-		
Select	Load Attributes	Copy Tab		

